



Guide handheld app

Connecting to sensor

1. Open the handheld app and tap on the sensor you would like to connect with.




2. Real-time spot measurements will appear once connected.




Downloading stored data from sensor


1. Tap on the download button in the top right corner.




2. Select your substrate type and tap on the “Download button”.



3. Wait till the measurements are finished downloading.



4. Once the download is completed, you will be prompted to share the file. You can choose from various applications supporting file-sharing such as Airdrop.




Creating a block measurement

1. Tap on the “Measurements”-tab.



2. This view shows all your previous measurements. Tap on “New measurement” to start one.



3. Provide the number of blocks inside your measurement, the number of measurements inside a block and the substrate type. After that, tap “next”.

12:02

NEW MEASUREMENT

Name
Measurement 3


Blocks
1 —●— 20

Measurements
1 —●— 24

Substrate type
MJ slabs 100

NEXT

4. You will be guided through each measurement. Wait for each measurement till proper values appear and tap “Save”.



5. After finishing all measurements, an overview will appear with a download option.



6. The download button opens a share-panel. You can choose from various applications supporting file-sharing such as Airdrop.

